

RUFFLE PILLOW

DESIGN BY ANNA GRIFFIN

SEWN BY JEAN ANN WRIGHT



FINISHED PILLOW:
24" SQUARE

What You'll Need:

1 yd #27258 teal

1/2 yd #27260-6 floral spray print

1/8 yd #27257-3 yellow

1-1/4 yd #27261-5 light aqua for ruffle
and pillow back

3/4 yd thin cotton batting

24" pillow form

1-1/2 yd 1/8" taupe twisted cord trim

2-1/2 yd 1/4" cotton cording

ANNA  GRIFFIN®

EXCLUSIVELY BY  Windham Fabrics

CUTTING INSTRUCTIONS

Note: All seams are 1/4"

Instructions to cut pillow front are on the diagram

- (1) 24-1/2" square #27261 light aqua for pillow back
- (3) 2" x width of fabric strips to cover 1/4" cotton cording
- (1) fussy cut labels with #5 from #27257 yellow

SEWING INSTRUCTIONS:

1. Sew the taupe twisted cord trim to the right side of the 12-1/2" center of the pillow with outside edge of cord even with raw edge of fabric square.
2. Sew the ruffle strips into one long strip and gather to fit around the outside of the center square. Match the raw edge of the gathered side of the ruffle to the raw edge of the center square and sew in place as close to the cord trim as possible. Use a zipper foot or cording foot to stitch closely.

3. Sew the #27258-teal borders to each side of the center square with ruffle and cording already stitched in place. Miter the corners of the borders and trim away excess fabric from the back.
4. Position the #5 label in the lower right corner of the pillow center and sew in place with raw edges exposed.
5. Layer the quilt top and batting and quilt the pillow center following the floral spray design. Quilt the borders in a free form feather design following the pattern of the fabric.
6. Sew the narrow strips cut for the cording into one long strip. Wrap around the cording and stitch in place using your zipper or cording foot. Pin the cording in place on the right side of the pillow top. Sew the welting to the right side of the pillow top.
7. Cross hatch the pillow back square at 2" intervals. Layer the pillow backing on top of the pillow front with right sides together. Sew all around leaving a 12" opening at the bottom. Stuff the pillow form inside and sew the opening together by hand

